


APU-Net Guide	Ver	Applicable OS
SPSS Amos Install Manual	2.0	Windows

- After applying for SPSS use, please check your email from the Academic Office and follow the steps below to install SPSS Amos and authenticate your license.
- The SPSS Amos installer and authentication code can be found from the [License] link in the email from the Academic Office sent to you after your application.
- SPSS Amos cannot be used on Mac PCs


## 1. Install SPSS Amos

1-1. Please download and run [SPSSA\_29.0\_MW\_ML.exe] from the [Amos Install folder]. Click [Next].




APU-Net Guide	Ver	Applicable OS
SPSS Amos Install Manual	2.0	Windows

1-2. Set "I accept the terms in the license agreement" and click [Next >].




1-3. Set the folder to install IBM SPSS Amos, and click [Next >].

It is recommended to install with the default settings (as is).




APU-Net Guide	Ver	Applicable OS
SPSS Amos Install Manual	2.0	Windows

1-4. Click [Install]. Installation of IBM SPSS Amos will begin.




1-5. When the installation of IBM SPSS Amos is completed, the following screen will be displayed.




APU-Net Guide	Ver	Applicable OS
SPSS Amos Install Manual	2.0	Windows

## 2. License Authorization

2-1. Launch [IBM SPSS Amos 29 License Authorization] from the Start menu.




2-2. Click [Next >].




APU-Net Guide	Ver	Applicable OS
SPSS Amos Install Manual	2.0	Windows

2-3. On the [Product Authorization] screen, select "Authorized user license (I purchased a single copy of the product)." and click [Next >].




2-4. On the [Enter Codes] screen, enter the "authentication code (20 alphanumeric characters)" and click [Add].

\*The authentication code can be found inside the provided folder




APU-Net Guide	Ver	Applicable OS
SPSS Amos Install Manual	2.0	Windows

2-5. On the [Enter codes] screen, move the code to the bottom as shown below and click "Next >".




2-6. On the [Internet Authentication Status] screen, when "Successfully processed all codes" is displayed in green letters, click [Next >].

\*If an error occurs in red letters, proceed to [step 3](#).




APU-Net Guide	Ver	Applicable OS
SPSS Amos Install Manual	2.0	Windows

2-7. After confirming that the license has been authenticated on the [Licensing Completed] screen, click [Finish].



### 3. Resetting the License


3-1. After license activation, make sure that "Authorization Error" is displayed in red text, then click [Next>].




APU-Net Guide	Ver	Applicable OS
SPSS Amos Install Manual	2.0	Windows

3-2. Follow the instructions on the next screen to paste the license code into the email body and send it to the specified recipient, then click [Finish].

- 1) Click "Copy" and paste the information into an email.
- 2) Type in subject line: "License Authorization"
- 3) Send to: spssls@us.ibm.com




3-3. You will receive an email within a few minutes, so repeat steps 2-1 to 2-3, then copy and paste the license code from the email on the screen in step 3-2, click [Add] to add it, and then click [Next>].



APU-Net Guide	Ver	Applicable OS
SPSS Amos Install Manual	2.0	Windows

3-4. On the next screen, make sure "Successfully processed all codes" is displayed in green text, then click [Next>].



3-5. On the next screen, confirm that license authentication is complete and click [Finish].

